# **Setup - Server Configuration Parameters, TBL**

#### **Page Contents**

- 1 Server Configuration
  - 1.1 Server Parameters
  - 1.2 General Database Parameters
  - 1.3 SWP Parameters
  - 1.4 LDAP Servers (Service Providers)
    - 1.4.1 Configuration parameters
  - 1.5 SMTP Server Parameters
  - 1.6 Advanced Parameters
  - 1.7 URI mappings
- 2 User Interface Configuration
- 3 Download Configuration Files

# **Server Configuration**

This first section contains the main systems-related settings for TBL (for persistence and other application settings, see Setup - TBL Configuration Parameters). Administrators can update the section via its **Edit** button and ensuring to click **Save Changes** when finished.

#### **Server Parameters**

Parameter	Default	Description
Server URL		This URL should be the TBL web-application's own <i>context path</i> , <b>without</b> a trailing slash "/". It enables email notifications with "live" TBL-server links (back to the webapp) for governance events or for tasks. For example, for the TBL (Tomcat) server, it would be something like: http://serverhostname/tbl  For TopBraid Composer - Maestro Edition, it would be: http://localhost/:8083
Show Hidden Files	false	During data selection, show all the files that are present on each project.

#### **General Database Parameters**

Parameter	Default	Description
Max Connections per Database	100	For each RDBMS (relational) or D2RQ database, the maximum number of active connections permitted.

#### **SWP Parameters**

Parameter	Default	Description
-----------	---------	-------------

Constraint violations block editing	false	If true then the SWA edit forms will report those SPIN constraint violations marked as spin:Error or spin:Fatal as errors that cannot be OKed by the confirm dialog. By default (false), all SPIN constraint violations are non-Fatal are reported as warnings that the user can manually bypass.
ui label function URI		The URI of a SPARQL function that takes a resource as argument and returns a string representation. If set, this will be used whenever ui:label is called, making it possible to define custom label algorithms in a single place.
ui:lib function is constant	false	True to have ui:lib() always return the static value "lib".
maximum number of table rows	1000	The maximum number of rows to be displayed by (search results) table widgets

### **LDAP Servers (Service Providers)**

TBL can support multiple LDAP service providers (e.g., multiple Active Directory domains or LDAP servers). For each one, click the plus sign "+" to create a new LDAP stanza (parameter group).



Before applying any LDAP changes, please double-check all settings for accuracy. Inconsistencies with remote LDAP systems could result in the loss of TBL permissions, which could be especially problematic for administrators (i.e., users having roles with AdministratorGrp group privileges; see Rights Management). Please verify before proceeding. Losing administrator permissions would block access to Administration pages, including this one, thereby requiring external access to the TBL system environment to modify the configuration files directly.

#### **Configuration parameters**

For each LDAP server, open **Server Configuration > Edit > Configuration parameters > "+"** and enter the following server parameters. To delete an LDAP server configuration, open **Edit** and click its "x".

Parameter	Default	Description
Connection URL		LDAP service provider's connection URL
Username for server connection		Username for connection login
Password for server connection		This appears only if other LDAP parameters are set, and it is set <i>after</i> <b>Save Changes</b> has completed.
User pattern string		Based on the <i>Tomcat JNDIRealm</i> (for LDAP), this is the <b>userSearch</b> and <b>userBase</b> (e.g., "sAMAccountName={0}, CN=Users, DC=sharepoint, DC=tqinc, DC=info")
Role definition base		roleBase: The base DN for role searches (e. g., "OU=Roles,DC=sharepoint,DC=tqinc, DC=info")
Role name identifier		roleName: The name of the attribute that has the role-entry's name (e.g., "cn")
Role search string		roleSearch: The LDAP search filter for selecting role entries (e.g., "(member={0})")

Membership search string	For certain LDAPs (e.g., <i>Active Directory</i> ), this is the reverse of roleSearch, used to
(OPTIONAL, Recommended)	find role memberships for a given user (e.g., "(memberOf={0})").

## **SMTP Server Parameters**

Parameter	Default	Description
SMTP Authentication On	false	Tells if smtp server requires authentication.
SMTP Server		Smtp Server to be used for sending emails in TopBraid Live.
SMTP Server Port Number	587	Port used by smtp Server.
SSL Enabled	false	If SSL for mail is on
SMTP Username		Username for authenticating on smtp server.
SMTP Password		This appears only if other SMTP parameters are set, and it is set <i>after</i> <b>Save Changes</b> has completed.

### **Advanced Parameters**

Parameter	Default	Description
Allow Anonymous Access	false	If no authentication scheme is used and this flag is true, anonymous access with READ and EXECUTE permission is allowed to the application.
Enable SPARQL updates	false	If true, then the SPARQL end point (servlet) will allow update requests.
Timeout on SPARQL Endpoint		If not set or 0, SPARQL endpoint has no timeout. Timeout is in milliseconds. If the timeout is reached, the system will throw a CancelQueryException to the user.
Enable Fair Locks	true	If true, then locks taken by TBL will use a first in first out queue, if false then order is less predictable.
Longer Stack Traces	false	Create longer stack traces, adding very large overhead. These are very useful for rapid resolution of certain types of problems. Set this parameter only if requested by TopQuadrant Customer Support.
Fail With Error on Design Inconsistency	false	When a possible software design inconsistency is detected, fail with an error.
Disable Lucene Indexing	false	Used for Search the EDG. If disabling is true, the indexing is off thereby using SPARQL search, and the syntax of users' search queries changes regarding the usage of explicit wildcard characters; see for User Interface - Overview: Lucene integration details.
Lucene Index Interval	60 minutes	Sets a custom interval time for reindexing graph's included in the Search the EDG configuration, if Lucene is enabled. Will read this value as minutes. The minimum time is 30 minutes.


Enable SPARQL Query Management	false	Enable the query management functionality to monitor currently running queries in the system. See also: Component Monitoring > Process Management.
Secure Storage encryption	PBEWithSHA1andDESede	Optionally changes the encryption algorithm for storing passwords in the secure storage file. If changed, please use a <b>new secure storage file</b> and <b>restart the server</b> .
Suppress Warnings of Possible Design Inconsistency	true	When a possible software design inconsistency is detected, and the system is not configured to fail, then suppress the warnings. Setting this parameter to false will result in logged error message of any design inconsistencies.
Temporary Graphs Time Out	2	The length of time to wait before a temporary graph can be garbage collected (minutes).
Use Saxon	false	Use Saxon rather than Xalan for XSLT/XML processing.
Verbose logging	false	If true, then some operations will send additional info to the log. This may slow down the server a bit.
Google Maps API Key		To enable Google Maps viewing functions in TopBraid, obtain an API key (string) from Google and enter it here.

## **URI** mappings

Parameter	Default	Description
Short Graph name		A tuple consisting of a graph (URI) and a short name. Can be used to abbreviate graphs in servlet calls. For example the SPIN template servlet handles abbreviated names such as /tbl/template/swa /GetResourceValues/kennedys? If you want to address the kennedys ontology with that URL, you need to add a short graph name that associates http://topbraid.org /examples/kennedys with the name "kennedys".

# **User Interface Configuration**

Some TopBraid TBL features support assigning language tags to string attribute values using a drop-down list when editing, for example:



To customize the list of available choices, go to the **Server Administration** page, then **Server Configuration Parameters**. The bottom of the Server Configuration Parameters screen has a space-delimited list where you can enter the language choices that will appear on TBL editing screens. Any codes can be entered, but the codes will interoperate better with other systems, such as Web browsers, if the ISO 639 language codes and, optionally, ISO 3166 country codes, are used. In the following, ISO codes for Spanish, English US English have been entered. These will be the only languages that appear in the language tag drop-down:



Be sure click Save Changes when finished.

### **Download Configuration Files**

Download general config graph	Click this link will download the current config.ttl from the system folder.
Downoad uiconfig graph	Click this link to download the current uiconfig.ui.ttl from the system folder.